

#016

CLOTH POTS

includes instructions
for small, medium and
large sized cloth pots

AMY KALLISSA



YOU'LL NEED...

the following supplies will make
1 small, 1 medium and 1 large sized cloth pot

- 1/2 m external fabric
- 1/2 m lining fabric
- 1/4 m stiff interfacing

step by step, photographic instructions
by

AMY KALLISSA
pretty . chic . handmade

WWW.AMYKALLISSA.COM

#AMYKALLISSA

© AMY KALLISSA 2012

BEFORE YOU START

- Be sure to read all instructions before you begin.
- All seams are $\frac{1}{4}$ inch allowance, unless otherwise stated.
- RST stands for “right sides together”, meaning that the right sides of the fabric should be facing each other when you piece them together and sew them.
- WOF means “Width of Fabric” The cutting instructions are based on an average fabric width of 44 inches.
- Cloth Pots can be made in all different sizes! These instructions include three different sizes of small, medium and large which make the cloth pots as pictured on the front cover, but you can change the measurements to make your Cloth Pots any size you like!

ASSEMBLY



Start by taking your outer fabric pieces and iron each piece to a separate piece of interfacing - this will create the outer walls.

CUTTING

SMALL

Cut 2 - 8" x 8" of outer fabric
Cut 2 - 8" x 8" of lining fabric
Cut 2 - 8" x 8" of interfacing

MEDIUM

Cut 2 - 10" x 8" of outer fabric
Cut 2 - 10" x 8" of lining fabric
Cut 2 - 10" x 8" of interfacing

LARGE

Cut 2 - 12" x 8" of outer fabric
Cut 2 - 12" x 8" of lining fabric
Cut 2 - 12" x 8" of interfacing




Take the outer walls and sew them RST down the sides and along the bottom, leaving the top open.



Where the side seams meet the bottom seam, cut the corners off without actually cutting where you've just sewn.



Press all three seams open.



Press the bottom seam against the right side seam.



With your quilting ruler, measure in 1 1/2" and mark a line across.


Repeat steps 5 and 6 with the bottom and left side seams.



Sew along both of the lines that you've just drawn.



Take your quilting ruler and cut the corners off, leaving a 1/4" seam allowance.



Take your lining fabrics and sew them RST down the left and right sides of the fabric. Along the bottom seam, leave a gap of approximately 2" in the middle of the seam, remembering to stitch back and forth when you stop and start so that your stitching won't come undone. This will create the lining piece.




Where the side seams meet the bottom seam, cut the corners off without actually cutting where you've just sewn.



Press all three seams open.




Press the bottom seam against the right side seam.



With your quilting ruler, measure in 1 1/2" and mark a line across.

Repeat steps 12 and 13 with the bottom and left side seams.



Sew along both of the lines that you've just drawn.



Take your quilting ruler and cut the corners off, leaving a 1/4" seam allowance.



Turn your lining piece so that the right side of the fabric is facing outwards.

Match the seams of the outer walls to the seams of your lining piece, and pin around the edges to keep in place.



Sew all the way around the top edge.



Turn your cloth pot, right side out through the 3" gap that you left in the bottom seam of the lining piece.

Shape your cloth pot into shape and press with an iron if and where needed.



Take the lining piece and pin the 2” gap closed. Sew together, wrong sides together. Taper each end of where you start and stop by curving in and out from the edge, and don’t forget to stitch back and forth at the start and finish to strengthen your stitches.



Push the lining back into the cloth pot and turn the top edge over as far as desired. Shape and press with iron as needed.

You’re all done! Take a pic and post to Facebook and Instagram with “#amykallissa” to show off to all of your family and friends!

AMY KALLISSA
pretty . chic . handmade

#016 CLOTH POT
DESIGNED BY AMY KALLISSA
DUPLICATION PROHIBITED
© OCTOBER 2012 AMY KALLISSA
WWW.AMYKALLISSA.COM